



MUSIC CD'S

- When you insert a Music CD, Autoplay should detect the CD and take some action based on your settings.

One action is to ask what to do:



- Autoplay settings can be found in Control Panel.



Choose what happens when you insert each type of media or device

☒ Use AutoPlay for all media and devices

Removable drives

 Removable drive Open folder to view files (File Explorer) ▾

☐ Choose what to do with each type of media

 Pictures Choose a default ▾

 Videos Choose a default ▾

 Music Choose a default ▾

 Mixed content Choose a default ▾

Camera storage

 Memory card Choose a default ▾

DVDs

 DVD movie Choose a default ▾

 Enhanced DVD movie Choose a default ▾

 Blank DVD Choose a default ▾

 DVD-Audio Choose a default ▾

Blu-ray discs

 Blu-ray disc movie Choose a default ▾

 Blank Blu-ray disc Choose a default ▾

CDs

 Audio CD Choose a default ▾

 Enhanced audio CD Choose a default ▾


 Blank CD Choose a default ▾

 Video CD Choose a default ▾

 Super Video CD Choose a default ▾

In this example, Autoplay is on but no settings have been set except for Removable Drive > Open Folder to View Files.

- For Music CD's this is one setting you could use:




With this setting, when I insert a Music CD, it should play automatically with Windows Media Player.


- Remember to SAVE your changes. SAVE is located at the bottom of the Autoplay page on the far right.

WINDOWS MEDIA PLAYER

- When Autoplay opens Windows Media Player, a small window will open and your music should be playing:



- Enlarge to full screen.
- In the upper right corner of Windows Media Player, click on this icon.
-



SWITCH TO LIBRARY




This is Windows Media Player in Library View.

Notice the RIP CD and RIP Settings on the tool bar.


RIP is a fancy word for COPY. This action will copy the selected music tracks to your PC. But first there are some settings:

RIP SETTINGS:

- Click on the arrow next to RIP SETTINGS:



Select MORE OPTIONS



RIP MUSIC tab

LOCATION


Format MP3

Move the slider
to Best Quality

Click OK to save

Back on the main window click on RIP CD

This window will open:



TIC Do
Not add

& Tic I understand then click OK

This Window shows the Rip Status

Rip settings ▼				
☒	#	Title	Length	Rip status
heart ☐	1	The Dusty Road We Know	3:56	Ripped to libra...
☐	2	Old Lou	3:03	Ripped to libra...
ry ☐	3	Go To Nashville	3:11	Ripped to libra...
☐	4	The Shed	2:40	Ripped to libra...
☐	5	You & My Guitar	2:47	Ripped to libra...
☐	6	The Least I Can Do (Son...	2:56	Ripped to libra...
☐	7	I Had A Dream	2:01	Ripped to libra...
☐	8	Someday An Eagle	2:45	Ripped to libra...
☐	9	See You Next Year, Mate	3:24	Ripped to libra...
☐	10	Alice Springs	2:50	Ripped to libra...
☐	11	Coober Pedy	4:49	Ripped to libra...
☐	12	Stan Coster (Poem)	1:31	Ripped to libra...
☐	13	Short Of A Quid	2:06	Ripped to libra...
☐	14	Goodbye Again	2:17	Ripped to libra...

After all tracks have been copied,
close WMP and go to file explorer > MUSIC

You will find a new folder with the artist name and subfolders
with the music files.